

```
# Global Postfix configuration file. This file lists only a subset
# of all parameters. For the syntax, and for a complete parameter
# list, see the postconf(5) manual page (command: "man 5 postconf").
#
# For common configuration examples, see BASIC_CONFIGURATION_README
# and STANDARD_CONFIGURATION_README. To find these documents, use
# the command "postconf html_directory readme_directory", or go to
# http://www.postfix.org/.
#
# For best results, change no more than 2-3 parameters at a time,
# and test if Postfix still works after every change.

# SOFT BOUNCE
#
# The soft_bounce parameter provides a limited safety net for
# testing. When soft_bounce is enabled, mail will remain queued
# that
# would otherwise bounce. This parameter disables locally-generated
# bounces, and prevents the SMTP server from rejecting mail
# permanently
# (by changing 5xx replies into 4xx replies). However, soft_bounce
# is no cure for address rewriting mistakes or mail routing
# mistakes.
#
#soft_bounce = no

# LOCAL PATHNAME INFORMATION
#
# The queue_directory specifies the location of the Postfix queue.
# This is also the root directory of Postfix daemons that run
# chrooted.
# See the files in examples/chroot-setup for setting up Postfix
# chroot
# environments on different UNIX systems.
#
#queue_directory = /var/spool/postfix

# The command_directory parameter specifies the location of all
# postXXX commands.
#
#command_directory = /usr/sbin

# The daemon_directory parameter specifies the location of all
# Postfix
# daemon programs (i.e. programs listed in the master.cf file). This
# directory must be owned by root.
#
#daemon_directory = /usr/lib/postfix

# The data_directory parameter specifies the location of Postfix-
# writable
# data files (caches, random numbers). This directory must be owned
# by the mail_owner account (see below).
#
```

```
data_directory = /var/lib/postfix
```

```
# QUEUE AND PROCESS OWNERSHIP
```

```
#
```

```
# The mail_owner parameter specifies the owner of the Postfix queue  
# and of most Postfix daemon processes. Specify the name of a user  
# account THAT DOES NOT SHARE ITS USER OR GROUP ID WITH OTHER  
ACCOUNTS
```

```
# AND THAT OWNS NO OTHER FILES OR PROCESSES ON THE SYSTEM. In  
# particular, don't specify nobody or daemon. PLEASE USE A DEDICATED  
# USER.
```

```
#
```

```
#mail_owner = postfix
```

```
# The default_privs parameter specifies the default rights used by  
# the local delivery agent for delivery to external file or command.  
# These rights are used in the absence of a recipient user context.  
# DO NOT SPECIFY A PRIVILEGED USER OR THE POSTFIX OWNER.
```

```
#
```

```
#default_privs = nobody
```

```
# INTERNET HOST AND DOMAIN NAMES
```

```
#
```

```
# The myhostname parameter specifies the internet hostname of this  
# mail system. The default is to use the fully-qualified domain name  
# from gethostname(). $myhostname is used as a default value for  
many
```

```
# other configuration parameters.
```

```
#
```

```
#myhostname = host.domain.tld
```

```
#myhostname = virtual.domain.tld
```

```
# The mydomain parameter specifies the local internet domain name.  
# The default is to use $myhostname minus the first component.  
# $mydomain is used as a default value for many other configuration  
# parameters.
```

```
#
```

```
#mydomain = domain.tld
```

```
# SENDING MAIL
```

```
#
```

```
# The myorigin parameter specifies the domain that locally-posted  
# mail appears to come from. The default is to append $myhostname,  
# which is fine for small sites. If you run a domain with multiple  
# machines, you should (1) change this to $mydomain and (2) set up  
# a domain-wide alias database that aliases each user to  
# user@that.users.mailhost.
```

```
#
```

```
# For the sake of consistency between sender and recipient  
addresses,
```

```
# myorigin also specifies the default domain name that is appended  
# to recipient addresses that have no @domain part.
```

```
#
```

```
# Debian GNU/Linux specific: Specifying a file name will cause the
```

```
# first line of that file to be used as the name. The Debian
default
# is /etc/mailname.
#
#myorigin = /etc/mailname
#myorigin = $myhostname
#myorigin = $mydomain

# RECEIVING MAIL

# The inet_interfaces parameter specifies the network interface
# addresses that this mail system receives mail on. By default,
# the software claims all active interfaces on the machine. The
# parameter also controls delivery of mail to user@[ip.address].
#
# See also the proxy_interfaces parameter, for network addresses
that
# are forwarded to us via a proxy or network address translator.
#
# Note: you need to stop/start Postfix when this parameter changes.
#
#inet_interfaces = all
#inet_interfaces = $myhostname
#inet_interfaces = $myhostname, localhost

# The proxy_interfaces parameter specifies the network interface
# addresses that this mail system receives mail on by way of a
# proxy or network address translation unit. This setting extends
# the address list specified with the inet_interfaces parameter.
#
# You must specify your proxy/NAT addresses when your system is a
# backup MX host for other domains, otherwise mail delivery loops
# will happen when the primary MX host is down.
#
#proxy_interfaces =
#proxy_interfaces = 1.2.3.4

# The mydestination parameter specifies the list of domains that
this
# machine considers itself the final destination for.
#
# These domains are routed to the delivery agent specified with the
# local_transport parameter setting. By default, that is the UNIX
# compatible delivery agent that lookups all recipients in /etc/
passwd
# and /etc/aliases or their equivalent.
#
# The default is $myhostname + localhost.$mydomain. On a mail
domain
# gateway, you should also include $mydomain.
#
# Do not specify the names of virtual domains - those domains are
# specified elsewhere (see VIRTUAL_README).
#
```

```

# Do not specify the names of domains that this machine is backup MX
# host for. Specify those names via the relay_domains settings for
# the SMTP server, or use permit_mx_backup if you are lazy (see
# STANDARD_CONFIGURATION_README).
#
# The local machine is always the final destination for mail
# addressed
# to user@[the.net.work.address] of an interface that the mail
# system
# receives mail on (see the inet_interfaces parameter).
#
# Specify a list of host or domain names, /file/name or type:table
# patterns, separated by commas and/or whitespace. A /file/name
# pattern is replaced by its contents; a type:table is matched when
# a name matches a lookup key (the right-hand side is ignored).
# Continue long lines by starting the next line with whitespace.
#
# See also below, section "REJECTING MAIL FOR UNKNOWN LOCAL USERS".
#
#mydestination = $myhostname, localhost.$mydomain, localhost
#mydestination = $myhostname, localhost.$mydomain, localhost,
#mydomain
#mydestination = $myhostname, localhost.$mydomain, localhost,
#mydomain,
#      mail.$mydomain, www.$mydomain, ftp.$mydomain

# REJECTING MAIL FOR UNKNOWN LOCAL USERS
#
# The local_recipient_maps parameter specifies optional lookup
# tables
# with all names or addresses of users that are local with respect
# to $mydestination, $inet_interfaces or $proxy_interfaces.
#
# If this parameter is defined, then the SMTP server will reject
# mail for unknown local users. This parameter is defined by
# default.
#
# To turn off local recipient checking in the SMTP server, specify
# local_recipient_maps = (i.e. empty).
#
# The default setting assumes that you use the default Postfix local
# delivery agent for local delivery. You need to update the
# local_recipient_maps setting if:
#
# - You define $mydestination domain recipients in files other than
#   /etc/passwd, /etc/aliases, or the $virtual_alias_maps files.
#   For example, you define $mydestination domain recipients in
#   the $virtual_mailbox_maps files.
#
# - You redefine the local delivery agent in master.cf.
#
# - You redefine the "local_transport" setting in main.cf.
#
# - You use the "luser_relay", "mailbox_transport", or

```

```

"fallback_transport"
#   feature of the Postfix local delivery agent (see local(8)).
#
# Details are described in the LOCAL_RECIPIENT_README file.
#
# Beware: if the Postfix SMTP server runs chrooted, you probably
have
# to access the passwd file via the proxymap service, in order to
# overcome chroot restrictions. The alternative, having a copy of
# the system passwd file in the chroot jail is just not practical.
#
# The right-hand side of the lookup tables is conveniently ignored.
# In the left-hand side, specify a bare username, an @domain.tld
# wild-card, or specify a user@domain.tld address.
#
#local_recipient_maps = unix:passwd.byname $alias_maps
#local_recipient_maps = proxy:unix:passwd.byname $alias_maps
#local_recipient_maps =

# The unknown_local_recipient_reject_code specifies the SMTP server
# response code when a recipient domain matches $mydestination or
# ${proxy,inet}_interfaces, while $local_recipient_maps is non-empty
# and the recipient address or address local-part is not found.
#
# The default setting is 550 (reject mail) but it is safer to start
# with 450 (try again later) until you are certain that your
# local_recipient_maps settings are OK.
#
unknown_local_recipient_reject_code = 550

# TRUST AND RELAY CONTROL

# The mynetworks parameter specifies the list of "trusted" SMTP
# clients that have more privileges than "strangers".
#
# In particular, "trusted" SMTP clients are allowed to relay mail
# through Postfix. See the smtpd_recipient_restrictions parameter
# in postconf(5).
#
# You can specify the list of "trusted" network addresses by hand
# or you can let Postfix do it for you (which is the default).
#
# By default (mynetworks_style = subnet), Postfix "trusts" SMTP
# clients in the same IP subnetworks as the local machine.
# On Linux, this does works correctly only with interfaces specified
# with the "ifconfig" command.
#
# Specify "mynetworks_style = class" when Postfix should "trust"
SMTP
# clients in the same IP class A/B/C networks as the local machine.
# Don't do this with a dialup site - it would cause Postfix to
"trust"
# your entire provider's network. Instead, specify an explicit
# mynetworks list by hand, as described below.

```

```

#
# Specify "mynetworks_style = host" when Postfix should "trust"
# only the local machine.
#
#mynetworks_style = class
#mynetworks_style = subnet
#mynetworks_style = host

# Alternatively, you can specify the mynetworks list by hand, in
# which case Postfix ignores the mynetworks_style setting.
#
# Specify an explicit list of network/netmask patterns, where the
# mask specifies the number of bits in the network part of a host
# address.
#
# You can also specify the absolute pathname of a pattern file
instead
# of listing the patterns here. Specify type:table for table-based
lookups
# (the value on the table right-hand side is not used).
#
#mynetworks = 168.100.189.0/28, 127.0.0.0/8
#mynetworks = $config_directory/mynetworks
#mynetworks = hash:/etc/postfix/network_table
mynetworks = 127.0.0.0/8, 5.44.100.230

# The relay_domains parameter restricts what destinations this
system will
# relay mail to. See the smtpd_recipient_restrictions description
in
# postconf(5) for detailed information.
#
# By default, Postfix relays mail
# - from "trusted" clients (IP address matches $mynetworks) to any
destination,
# - from "untrusted" clients to destinations that match
$relay_domains or
# subdomains thereof, except addresses with sender-specified
routing.
# The default relay_domains value is $mydestination.
#
# In addition to the above, the Postfix SMTP server by default
accepts mail
# that Postfix is final destination for:
# - destinations that match $inet_interfaces or $proxy_interfaces,
# - destinations that match $mydestination
# - destinations that match $virtual_alias_domains,
# - destinations that match $virtual_mailbox_domains.
# These destinations do not need to be listed in $relay_domains.
#
# Specify a list of hosts or domains, /file/name patterns or
type:name
# lookup tables, separated by commas and/or whitespace. Continue
# long lines by starting the next line with whitespace. A file name

```

```

# is replaced by its contents; a type:name table is matched when a
# (parent) domain appears as lookup key.
#
# NOTE: Postfix will not automatically forward mail for domains that
# list this system as their primary or backup MX host. See the
# permit_mx_backup restriction description in postconf(5).
#
#relay_domains = $mydestination

# INTERNET OR INTRANET

# The relayhost parameter specifies the default host to send mail to
# when no entry is matched in the optional transport(5) table. When
# no relayhost is given, mail is routed directly to the destination.
#
# On an intranet, specify the organizational domain name. If your
# internal DNS uses no MX records, specify the name of the intranet
# gateway host instead.
#
# In the case of SMTP, specify a domain, host, host:port,
# [host]:port,
# [address] or [address]:port; the form [host] turns off MX lookups.
#
# If you're connected via UUCP, see also the default_transport
# parameter.
#
#relayhost = $mydomain
#relayhost = [gateway.my.domain]
#relayhost = [mailserver.isp.tld]
#relayhost = uucphost
relayhost = 5.44.100.230

# REJECTING UNKNOWN RELAY USERS
#
# The relay_recipient_maps parameter specifies optional lookup
# tables
# with all addresses in the domains that match $relay_domains.
#
# If this parameter is defined, then the SMTP server will reject
# mail for unknown relay users. This feature is off by default.
#
# The right-hand side of the lookup tables is conveniently ignored.
# In the left-hand side, specify an @domain.tld wild-card, or
# specify
# a user@domain.tld address.
#
#relay_recipient_maps = hash:/etc/postfix/relay_recipients

# INPUT RATE CONTROL
#
# The in_flow_delay configuration parameter implements mail input
# flow control. This feature is turned on by default, although it
# still needs further development (it's disabled on SCO UNIX due
# to an SCO bug).

```

```
#
# A Postfix process will pause for $in_flow_delay seconds before
# accepting a new message, when the message arrival rate exceeds the
# message delivery rate. With the default 100 SMTP server process
# limit, this limits the mail inflow to 100 messages a second more
# than the number of messages delivered per second.
#
# Specify 0 to disable the feature. Valid delays are 0..10.
#
#in_flow_delay = 1s

# ADDRESS REWRITING
#
# The ADDRESS_REWRITING_README document gives information about
# address masquerading or other forms of address rewriting including
# username->Firstname.Lastname mapping.

# ADDRESS REDIRECTION (VIRTUAL DOMAIN)
#
# The VIRTUAL_README document gives information about the many forms
# of domain hosting that Postfix supports.

# "USER HAS MOVED" BOUNCE MESSAGES
#
# See the discussion in the ADDRESS_REWRITING_README document.

# TRANSPORT MAP
#
# See the discussion in the ADDRESS_REWRITING_README document.

# ALIAS DATABASE
#
# The alias_maps parameter specifies the list of alias databases
# used
# by the local delivery agent. The default list is system dependent.
#
# On systems with NIS, the default is to search the local alias
# database, then the NIS alias database. See aliases(5) for syntax
# details.
#
# If you change the alias database, run "postalias /etc/aliases" (or
# wherever your system stores the mail alias file), or simply run
# "newaliases" to build the necessary DBM or DB file.
#
# It will take a minute or so before changes become visible. Use
# "postfix reload" to eliminate the delay.
#
#alias_maps = dbm:/etc/aliases
#alias_maps = hash:/etc/aliases
#alias_maps = hash:/etc/aliases, nis:mail.aliases
#alias_maps = netinfo:/aliases

# The alias_database parameter specifies the alias database(s) that
# are built with "newaliases" or "sendmail -bi". This is a separate
```



```

# configuration parameter, because alias_maps (see above) may
# specify
# tables that are not necessarily all under control by Postfix.
#
#alias_database = dbm:/etc/aliases
#alias_database = dbm:/etc/mail/aliases
#alias_database = hash:/etc/aliases
#alias_database = hash:/etc/aliases, hash:/opt/majordomo/aliases

# ADDRESS EXTENSIONS (e.g., user+foo)
#
# The recipient_delimiter parameter specifies the separator between
# user names and address extensions (user+foo). See canonical(5),
# local(8), relocated(5) and virtual(5) for the effects this has on
# aliases, canonical, virtual, relocated and .forward file lookups.
# Basically, the software tries user+foo and .forward+foo before
# trying user and .forward.
#
#recipient_delimiter = +

# DELIVERY TO MAILBOX
#
# The home_mailbox parameter specifies the optional pathname of a
# mailbox file relative to a user's home directory. The default
# mailbox file is /var/spool/mail/user or /var/mail/user. Specify
# "Maildir/" for qmail-style delivery (the / is required).
#
#home_mailbox = Mailbox
#home_mailbox = Maildir/

# The mail_spool_directory parameter specifies the directory where
# UNIX-style mailboxes are kept. The default setting depends on the
# system type.
#
#mail_spool_directory = /var/mail
#mail_spool_directory = /var/spool/mail

# The mailbox_command parameter specifies the optional external
# command to use instead of mailbox delivery. The command is run as
# the recipient with proper HOME, SHELL and LOGNAME environment
# settings.
# Exception: delivery for root is done as $default_user.
#
# Other environment variables of interest: USER (recipient
# username),
# EXTENSION (address extension), DOMAIN (domain part of address),
# and LOCAL (the address localpart).
#
# Unlike other Postfix configuration parameters, the mailbox_command
# parameter is not subjected to $parameter substitutions. This is to
# make it easier to specify shell syntax (see example below).
#
# Avoid shell meta characters because they will force Postfix to run
# an expensive shell process. Procmail alone is expensive enough.

```

```
#
# IF YOU USE THIS TO DELIVER MAIL SYSTEM-WIDE, YOU MUST SET UP AN
# ALIAS THAT FORWARDS MAIL FOR ROOT TO A REAL USER.
#
#mailbox_command = /usr/bin/procmail
#mailbox_command = /usr/bin/procmail -a "$EXTENSION"

# The mailbox_transport specifies the optional transport in
master.cf
# to use after processing aliases and .forward files. This parameter
# has precedence over the mailbox_command, fallback_transport and
# luser_relay parameters.
#
# Specify a string of the form transport:nexthop, where transport is
# the name of a mail delivery transport defined in master.cf. The
# :nexthop part is optional. For more details see the sample
transport
# configuration file.
#
# NOTE: if you use this feature for accounts not in the UNIX
password
# file, then you must update the "local_recipient_maps" setting in
# the main.cf file, otherwise the SMTP server will reject mail for
# non-UNIX accounts with "User unknown in local recipient table".
#
# Cyrus IMAP over LMTP. Specify ``lmtputx cmd="lmtpd"
# listen="/var/imap/socket/lmtp" prefork=0'' in cyrus.conf.
#mailbox_transport = lmtp:unix:/var/imap/socket/lmtp
#
# Cyrus IMAP via command line. Uncomment the "cyrus...pipe" and
# subsequent line in master.cf.
#mailbox_transport = cyrus

# The fallback_transport specifies the optional transport in
master.cf
# to use for recipients that are not found in the UNIX passwd
database.
# This parameter has precedence over the luser_relay parameter.
#
# Specify a string of the form transport:nexthop, where transport is
# the name of a mail delivery transport defined in master.cf. The
# :nexthop part is optional. For more details see the sample
transport
# configuration file.
#
# NOTE: if you use this feature for accounts not in the UNIX
password
# file, then you must update the "local_recipient_maps" setting in
# the main.cf file, otherwise the SMTP server will reject mail for
# non-UNIX accounts with "User unknown in local recipient table".
#
#fallback_transport = lmtp:unix:/file/name
#fallback_transport = cyrus
#fallback_transport =
```

```

# The luser_relay parameter specifies an optional destination
address
# for unknown recipients. By default, mail for unknown@
$mydestination,
# unknown@[$inet_interfaces] or unknown[$proxy_interfaces] is
returned
# as undeliverable.
#
# The following expansions are done on luser_relay: $user (recipient
# username), $shell (recipient shell), $home (recipient home
directory),
# $recipient (full recipient address), $extension (recipient address
# extension), $domain (recipient domain), $local (entire recipient
# localpart), $recipient_delimiter. Specify ${name?value} or
# ${name:value} to expand value only when $name does (does not)
exist.
#
# luser_relay works only for the default Postfix local delivery
agent.
#
# NOTE: if you use this feature for accounts not in the UNIX
password
# file, then you must specify "local_recipient_maps =" (i.e. empty)
in
# the main.cf file, otherwise the SMTP server will reject mail for
# non-UNIX accounts with "User unknown in local recipient table".
#
#luser_relay = $user@other.host
#luser_relay = $local@other.host
#luser_relay = admin+$local

# JUNK MAIL CONTROLS
#
# The controls listed here are only a very small subset. The file
# SMTPD_ACCESS_README provides an overview.

# The header_checks parameter specifies an optional table with
patterns
# that each logical message header is matched against, including
# headers that span multiple physical lines.
#
# By default, these patterns also apply to MIME headers and to the
# headers of attached messages. With older Postfix versions, MIME
and
# attached message headers were treated as body text.
#
# For details, see "man header_checks".
#
#header_checks = regexp:/etc/postfix/header_checks

# FAST ETRN SERVICE
#
# Postfix maintains per-destination logfiles with information about

```

```

# deferred mail, so that mail can be flushed quickly with the SMTP
# "ETRN domain.tld" command, or by executing "sendmail -
qRdomain.tld".
# See the ETRN_README document for a detailed description.
#
# The fast_flush_domains parameter controls what destinations are
# eligible for this service. By default, they are all domains that
# this server is willing to relay mail to.
#
#fast_flush_domains = $relay_domains

# SHOW SOFTWARE VERSION OR NOT
#
# The smtpd_banner parameter specifies the text that follows the 220
# code in the SMTP server's greeting banner. Some people like to see
# the mail version advertised. By default, Postfix shows no version.
#
# You MUST specify $myhostname at the start of the text. That is an
# RFC requirement. Postfix itself does not care.
#
#smtpd_banner = $myhostname ESMTP $mail_name
#smtpd_banner = $myhostname ESMTP $mail_name ($mail_version)
smtpd_banner = $myhostname ESMTP $mail_name (Debian/GNU)

# PARALLEL DELIVERY TO THE SAME DESTINATION
#
# How many parallel deliveries to the same user or domain? With
local
# delivery, it does not make sense to do massively parallel delivery
# to the same user, because mailbox updates must happen
sequentially,
# and expensive pipelines in .forward files can cause disasters when
# too many are run at the same time. With SMTP deliveries, 10
# simultaneous connections to the same domain could be sufficient to
# raise eyebrows.
#
# Each message delivery transport has its
XXX_destination_concurrency_limit
# parameter. The default is $default_destination_concurrency_limit
for
# most delivery transports. For the local delivery agent the default
is 2.

#local_destination_concurrency_limit = 2
#default_destination_concurrency_limit = 20

# DEBUGGING CONTROL
#
# The debug_peer_level parameter specifies the increment in verbose
# logging level when an SMTP client or server host name or address
# matches a pattern in the debug_peer_list parameter.
#
#debug_peer_level = 2

```

```

# The debug_peer_list parameter specifies an optional list of domain
# or network patterns, /file/name patterns or type:name tables. When
# an SMTP client or server host name or address matches a pattern,
# increase the verbose logging level by the amount specified in the
# debug_peer_level parameter.
#
#debug_peer_list = 127.0.0.1
#debug_peer_list = some.domain

# The debugger_command specifies the external command that is
# executed
# when a Postfix daemon program is run with the -D option.
#
# Use "command .. & sleep 5" so that the debugger can attach before
# the process marches on. If you use an X-based debugger, be sure to
# set up your XAUTHORITY environment variable before starting
# Postfix.
#
debugger_command =
    PATH=/bin:/usr/bin:/usr/local/bin:/usr/X11R6/bin
    ddd $daemon_directory/$process_name $process_id & sleep 5

# If you can't use X, use this to capture the call stack when a
# daemon crashes. The result is in a file in the configuration
# directory, and is named after the process name and the process ID.
#
# debugger_command =
#     PATH=/bin:/usr/bin:/usr/local/bin; export PATH; (echo cont;
#     echo where) | gdb $daemon_directory/$process_name
#     $process_id 2>&1
#     >$config_directory/$process_name.$process_id.log & sleep 5
#
# Another possibility is to run gdb under a detached screen session.
# To attach to the screen session, su root and run "screen -r
# <id_string>" where <id_string> uniquely matches one of the
# detached
# sessions (from "screen -list").
#
# debugger_command =
#     PATH=/bin:/usr/bin:/sbin:/usr/sbin; export PATH; screen
#     -dmS $process_name gdb $daemon_directory/$process_name
#     $process_id & sleep 1

# INSTALL-TIME CONFIGURATION INFORMATION
#
# The following parameters are used when installing a new Postfix
# version.
#
# sendmail_path: The full pathname of the Postfix sendmail command.
# This is the Sendmail-compatible mail posting interface.
#
sendmail_path = /usr/sbin/sendmail

```

```

# newaliases_path: The full pathname of the Postfix newaliases
command.
# This is the Sendmail-compatible command to build alias databases.
#
newaliases_path = /usr/bin/newaliases

# mailq_path: The full pathname of the Postfix mailq command. This
# is the Sendmail-compatible mail queue listing command.
#
mailq_path = /usr/bin/mailq

# setgid_group: The group for mail submission and queue management
# commands. This must be a group name with a numerical group ID
that
# is not shared with other accounts, not even with the Postfix
account.
#
setgid_group = postdrop

# html_directory: The location of the Postfix HTML documentation.
#
html_directory = no

# manpage_directory: The location of the Postfix on-line manual
pages.
#
manpage_directory = /usr/share/man

# sample_directory: The location of the Postfix sample configuration
files.
# This parameter is obsolete as of Postfix 2.1.
#
sample_directory = no

# readme_directory: The location of the Postfix README files.
#
readme_directory = no
inet_protocols = ipv4
myhostname = bangenberg.de
mydomain = bangenberg.de
mydestination = vs4155.fra1.alvotech.net,
localhost.fra1.alvotech.net, , localhost, bangenberg.de
alias_maps = hash:/etc/aliases
alias_database = hash:/etc/aliases
mailbox_transport = lmtp:unix:/var/run/cyrus/socket/lmtp
fallback_transport = lmtp:unix:/var/run/cyrus/socket/lmtp

# TLS fuer den E-Mailversand
#
# Aktiviert TLS
smtp_use_tls = yes
# Aktiviert das Logging
smtp_tls_loglevel = 1
# Unverschlüsselte Verbindung erlauben (may = entscheidet der

```

```
Client)
smtp_tls_security_level      = may
# Pfade zu den Keys
smtp_tls_cert_file          = /etc/ssl/private/bangenberg.de/
bangenberg.cert
smtp_tls_key_file           = /etc/ssl/private/bangenberg/
bangenberg.key
##smtp_tls_CAfile           = /etc/ssl/private/bangenberg.de/
ca.pem
smtp_tls_note_starttls_offer = yes
smtp_tls_session_cache_database = btree:${data_directory}/
smtp_scache
smtp_tls_note_starttls_offer = yes
smtp_tls_CApath = /etc/ssl/certs

# SASL SUPPORT FOR SERVERS
#
# The following options set parameters needed by Postfix to enable
# Cyrus-SASL support for authentication of mail servers.
#
smtp_sasl_auth_enable = yes
smtp_sasl_password_maps = hash:/etc/postfix/sasl_passwd
smtp_sasl_security_options =
```